Visited 11/22/2019



Request an Appointment

Find a Doctor

Find a Job

Give Now

Log in to Patient Account

English

Patient Care & Health Information

Tests & Procedures


Ankle-brachial index



About

Overview

The ankle-brachial index test is a quick, noninvasive way to check for peripheral artery disease (PAD). The disease occurs when narrowed arteries reduce the blood flow to your limbs. PAD can cause leg pain when walking and increases the risk of heart attack and stroke.



Print

Ankle-brachial index

The ankle-brachial index test compares the blood pressure measured at your ankle with the blood pressure measured at your arm. A low ankle-brachial index number can indicate narrowing or blockage of the arteries in your legs.

You may have ankle-brachial index testing before and immediately after walking on a treadmill. An exercise ankle-brachial index test can assess the severity of the narrowed arteries during walking.

Advertisement

Mayo Clinic does not endorse companies or products. Advertising revenue supports our not-for-profit mission.

Advertising & Sponsorship

Policy | Opportunities | Ad Choices |

Mayo Clinic Marketplace

Check out these best-sellers and special offers on books and newsletters from Mayo Clinic.

NEW – Guide to Fibromyalgia

Instant access – Mayo Clinic Health Letter

Diabetes? This diet works ...

Stop osteoporosis in its tracks

The Mayo Clinic Diet Online

Products & Services

Book: Mayo Clinic Healthy Heart for Life!

Why it's done

The ankle-brachial index test is done to check for PAD — narrowed arteries that reduce blood flow, usually in your legs. Research indicates that PAD affects about 10 percent of people over age 55.

Your doctor might recommend an ankle-brachial index test if you have leg pain while walking or risk factors for PAD, such as:

- History of tobacco use
- Diabetes
- High blood pressure
- High cholesterol
- Restricted blood flow (atherosclerosis) in other parts of your body

More Information

Arteriosclerosis / atherosclerosis

Claudication

Peripheral artery disease

Request an Appointment at Mayo Clinic

Risks

You may feel some discomfort when the blood pressure cuffs inflate on your arm and ankle. But this discomfort is temporary and should stop when the air is released from the cuff.

If you have severe leg pain, your doctor may recommend a different imaging test of the arteries in your legs.

How you prepare

Generally, you won't need to follow any special instructions before your appointment to have an ankle-brachial index test performed. You may want to wear loose, comfortable clothing that allows the technician performing your ankle-brachial index test to easily place a blood pressure cuff on your ankle and upper arm.

What you can expect

During the procedure

You likely will be asked to rest for 5 to 30 minutes before the test.

Typically, you lie on a table on your back, and a technician measures your blood pressure in both arms and both ankles, using an inflatable cuff and a hand-held ultrasound device that's pressed on your skin. The device uses sound waves to produce images and allows your pulse to be heard in your ankle arteries after the cuff is deflated.

After the procedure

The ankle-brachial index test should take only a few minutes. You don't need to follow any special precautions afterward. Your doctor will discuss your test result with you.

Results

Your doctor uses the blood pressure measurements from your arms and ankles to calculate your ankle-brachial index.

Based on the number your doctor calculates, your anklebrachial index may show you have:

- No blockage (1.0 to 1.4). An ankle-brachial index number in this range suggests that you probably don't have PAD. But if you have symptoms of PAD, your doctor might perform an exercise ankle-brachial index test.
- Borderline blockage (0.91 to 0.99). An ankle-brachial index number is this range indicates that you have borderline PAD. Your doctor might recommend an exercise ankle-brachial index test.
- PAD (less than 0.90). An ankle-brachial index number in this range is considered abnormal and indicates a diagnosis of PAD. Your doctor may recommend additional testing, such as ultrasound or angiography, to view the arteries in your legs.

If you have severe diabetes or significantly blocked arteries, your doctor may need to read your blood pressure at your big toe (toe-brachial index) to get an accurate test result.

Depending on the severity of your blockage, your doctor may recommend:

- Lifestyle changes
- Medication
- Surgery to treat PAD

By Mayo Clinic Staff

Request an Appointment at Mayo Clinic

Share on: Facebook Twitter Print Jan. 10, 2018

Show references ¬